

# Instalar Nextcloud

## Requisitos

- [Docker Engine](#)
- [Nginx proxy manager](#)
- Un dominio/subdominio

## Instalación

Crear las carpetas `mkdir -p docker/nextcloud`.

Crear el archivo `docker-compose.yml`.

```
volumes:
  nextcloud_aio_mastercontainer:
    name: nextcloud_aio_mastercontainer


services:
  nextcloud:
    image: nextcloud/all-in-one:latest
    restart: unless-stopped
    container_name: nextcloud-aio-mastercontainer
    volumes:
      - nextcloud_aio_mastercontainer:/mnt/docker-aio-config
      - /var/run/docker.sock:/var/run/docker.sock:ro
    ports:
      - 8080:8080 # change the port on the left side if it's already in use on your host
system.
    environment:
      - APACHE_PORT=11000 # change this port number if 11000 is already in use on your host
system.
      - APACHE_DISABLE_REWRITE_IP=1
```

```
- NEXTCLOUD_TRUSTED_DOMAINS=nextcloud.dominio.com 127.0.0.1 # Your domain name + proxy host IP
- TRUSTED_PROXIES=127.0.0.1 # proxy host IP
- NEXTCLOUD_DATADIR=/mnt/big_storage/nextcloud
```

Una vez creado ejecutar `docker-compose up -d`.

# Configurar Nginx proxy manager


Acceder a la pagina de Nginx proxy manager y configurar el proxy.



The image shows a screenshot of the 'Edit Proxy Host' configuration page in Nginx Proxy Manager. The page has a title bar with 'Edit Proxy Host' and a close button. Below the title bar are four tabs: 'Details' (selected), 'Custom locations', 'SSL', and 'Advanced'. The main content area is divided into several sections:

- Domain Names \***: A text input field containing a greyed-out placeholder.
- Scheme \***: A dropdown menu with 'http' selected.
- Forward Hostname / IP \***: A text input field containing '192.168.18.6'.
- Forward Port \***: A text input field containing '11000'.
- Cache Assets**: A toggle switch that is currently turned off.
- Block Common Exploits**: A toggle switch that is currently turned on.
- Websockets Support**: A toggle switch that is currently turned on.
- Access List**: A text input field containing 'Publicly Accessible'.

At the bottom right of the form, there are two buttons: 'Cancel' and 'Save'.



# Configurar Nextcloud AIO

Acceder

Poner el dominio que vamos a usar, configurar las aplicaciones que queremos y la hora.

Esperar a que se instale.


Una vez este todo instalado accedemos con el usuario y contraseña que nos ha dado.

# Nextcloud AIO v9.0.1

You are running the **latest** channel. ([Logs](#))

Initial Nextcloud username: **admin**

Initial Nextcloud password:



[Open your Nextcloud](#) ↗

If your Nextcloud does not open when clicking the button above, see [this documentation](#)

► [Click here to view the current AIO config and documentation links](#)

## Containers

- Apache ([Running](#))
- Database ([Running](#))
- Nextcloud ([Running](#))
- Notify Push ([Running](#))
- Redis ([Running](#))
- Imaginary ([Running](#))
- Docker Socket Proxy ([Running](#))

Your containers are up-to-date.

[Stop containers](#)

En la zona de errores tendremos un error que indica que no tenemos establecida una región de teléfono predeterminada, la establecemos con el siguiente comando:

```
sudo docker exec --user www-data nextcloud-aio-nextcloud php occ config:system:set default_phone_region --value="ES"
```

## Configurar correo electrónico

Crear una contraseña de aplicación con una cuenta de Gmail.

## Servidor de correo electrónico i

Es importante configurar este servidor para que pueda enviar correos, por ejemplo para cambios de contraseñas y notificaciones.

Modo de envío SMTP

Cifrado Ninguno/ST...

Desde la dirección [redacted] @ gmail.com

Dirección del servidor smtp.gmail.com : 587

Autenticación  Se necesita autenticación

Credenciales [redacted] @... \*\*\*\*\*

Guardar

Comprobar y verificar configuración de correo

Enviar mensaje

Revision #1

Created 2024-08-14 19:51:42 UTC by PabloMP

Updated 2024-08-14 19:57:27 UTC by PabloMP